



DragonView™

Installation Guide

US English



4340 South Monaco Street, Fourth Floor
Denver, Colorado 80237
Phone: 720.249.2100

© 2004-2010 Rivet Software, Inc. All rights reserved. Printed in the United States of America.

The following are trademarks or registered trademarks of Rivet Software: Dragon Tag, Dragon View, Hoppers, and Rivet. XBRL and Extensible Business Reporting Language are registered trademarks of XBRL International, Inc. All other names and marks are the property of their respective owners.

Microsoft, Microsoft Excel, and Microsoft Windows are all registered trademarks of the Microsoft Corporation.

This document is provided “as is” with no warranties, whatsoever. Rivet Software disclaims all liability, including liability for infringement of any proprietary rights, arising from use of the products described or from the information in this document. Rivet Software assumes no responsibility for errors or omissions in this document; nor does Rivet Software make any commitment to update the information contained herein.

The products described herein are intended solely for use in accordance with all applicable laws and treaties. It is illegal to reproduce, distribute, publicly display, or create derivative works of copyrighted materials without permission from the copyright owner. It is the responsibility of the person using these products to obtain any necessary permissions prior to reproducing, distributing, publicly displaying, or creating derivative works of any such items.

Rivet Software may have patents or pending patent applications, trademarks, copyrights, or other intellectual property rights that relate to the described subject matter. The furnishing of this document does not provide any license, express or implied, to any such patents, trademarks, copyrights, or other intellectual property rights, except that a license is hereby granted to copy and reproduce this document for internal use only.

Installing Dragon View

This Guide directs you through the procedure to install Dragon View. It includes the following topics:

- Hardware requirements
- Software requirements
- Installation procedure
- Activation procedure

Hardware Requirements

The following hardware requirements are recommended when installing and running the Dragon View Application.

Processor/CPU

- Intel Pentium 4 or higher
- AMD Athlon/Duron or higher

Memory

- 256 MB minimum
- 512 MB or higher recommended

Disk Space

- Installation footprint: 17 MB
- XBRL taxonomy space required dependent on number of taxonomies required

NOTE: XBRL taxonomies range in size from less than .5 MB to 5 MB.

Software Requirements

The following outlines the minimum requirements for installing and using Dragon View.

Supported Operating Systems

- Microsoft Windows® Vista Business Edition
- Microsoft Windows XP Professional Edition
- Microsoft Windows 7 Professional Edition
- Dragon View Installation Guide 5

- Microsoft Windows 2000 Professional (SP3 or SP4)

Supported Versions of Microsoft Office

- Microsoft Office 2007
- Microsoft Office 2003
- Microsoft Office XP (2002)
- Microsoft Office 2000

Required Components

- Microsoft .NET Framework 2.0

NOTE: The Microsoft .NET Framework is automatically installed with Microsoft applications such as Office 2003 and Windows XP Professional. Please use the Windows Control Panel's Add/Remove Programs feature to check to see if the Microsoft .NET Framework is already installed. For information on downloading and installing the correct version and service pack level, see "Installation Procedure" below.

Installation Procedure

The installation of Dragon View uses an easy to comprehend setup wizard that guides you through the installation process. To install Dragon View, please do the following:

1. Download the installation routine from the Rivet Software Product page. You can either download the self-extracting .EXE or the compressed .ZIP file.
2. Unzip the Dragon View Setup.exe file to a temporary folder.
3. Run the Setup.exe file that you unzipped.
4. Review the End User License Agreement (EULA) and click "I Accept" and "Next:" if you agree to the terms; if you do not agree with the terms of the EULA, click "I Do Not Agree" and you will exit the setup wizard.
5. You will be prompted to install Dragon View in the default folder of:

`c:\program files\Rivet\Rivet Dragon View`

It is recommended that you accept this installation location.

6. Click Next to accept the folder location.
7. Click Install to begin the installation.
8. When the installation completes, click Finish.